Python-Flask SW Installation Instructions For Windows

Markus Veijola June 2015



Installation Instructions

- * Download the Python installation file (.msi) from this Python3.4.3
- * At the moment of writing this document the latest version is 3.4.3
- * After download just start the installation wizard "python-3.4.3.msi) (from downloads folder) and follow the instructions.
- * After installation the python is installed in C:\Python34 if you did not change anything during installation.

Installation Instructions

- Next you need to add few paths in PATH variable in windows environment.
- * The paths you need to include are
 - * C:\Python34
 - * C:\Python34\Scripts
- * To do this open start menu. Select Control Panel ->System and Security->System->Advanced System Settings
- * From opened windows press "Environment Variables" button.
- * Select "PATH" environment variable from upper window and press edit. Go end of the line and append previously mentioned paths there separeated by ";".



Installation Instructions

- Open command prompt and try following commands:
 - * python –version
 - * pip –version
- * If you get version number after both command the Python environment is installed correctly in to your system.
- * Next create a virtual environment for you projects (this means that modules etc. Are not installed system wide and you get yuor own sandbox for your project)
- * To create virtual environment create a working directory fot your project i.e. C:\Python_codes\my_first_project.
- * Open CMD in your working directory. Execute next command:
 - * python –m venv flask
- Above command creates a private version of your Python interpreter inside a folder named flask



Activate Vitrualenv

- * Next thing to do is to activate the created virtual environment.
- * From CMD execute next command:

flask\Scripts\activate



- * Next you need to install the needed Flask modules. In this training we need several modules to be installed. To do this open command prompt in your working directory Scripts folder i.e. C:\Python_codes\my_firts_project\flask\Scripts
- * Execute next commands in this folder:
 - * pip install flask
 - pip install flask-login
 - pip install flask-openid
 - pip install flask-mail
 - * pip install flask-sqlalchemy
 - * pip install sqlalchemy-migrate
 - pip install flask-whooshalchemy
 - * pip install flask-wtf
 - pip install flask-babel
 - pip install guess language
 - pip install flipflop
 - pip install coverage



- * Go to root of your working directory i.e. in our example C:\Python_codes\my_first_project.
- * Inside a root directory create next kind of folder structure:
- * my_first_project
 - * app
 - * app\static
 - * app\templates
 - * tmp
 - flask (this was created previously as virtual env)



- * Go to the app folder and append __init__.py file in this directory.
- Files named __init__.py are used to mark directories on disk as Python package directories and are usually empty files.
- * This file ensures that you can import .py files as modules in subdirectories etc. in your project. For example if you have next kind of structure...:
 - * C:\my_project\app__init__.py
 - * C:\my project\app\nice module.py
- * ... makes possible to import nice_module.py in other python files as follow:

```
import app.nice_module
#or
```

from app import nice module

* If you remove the __init__.py file, Python will no longer look for submodules inside that directory, so attempts to import the module will fail.



* Now append next code in your __init__.py file (NOTE the file name has two underscores!!!!):

```
from flask import Flask
```

```
app = Flask(__name__)
from app import views
```



* Next create a file named views.py inside the app folder and apend next code there:

from app import app

@app.route('/')
 def root():
return "Hello, World!"



- * The final step to have a fully working web application is to create a script that starts up the development web server with our application.
- * Let's call this script run.py, and put it in the root folder and fill it up with next code:

#!flask/bin/python
from app import app
app.run(debug=True)

- * Next we can test that our Python flask environment works.
- * Execute the run.py with next command:
 - * flask\Scripts\python run.py
- * NOTE! The prvious command uses Python interpreter from our virtual environment not form system level. This is important since we installed the Flask environment in virtual environment which is not available in system level interpreter.
- * If everything went ok you should see something following in command prompt:
 - * * Running on http://127.0.0.1:5000/ (Press CTRL+C to quit)



* Now open browser window write next url address localhost:5000 and you should see text "hello world" in browser window. If so, you are ready to go with Python-Flask! Enjoy!